

Allesee Orthodontic Appliances

COMMUNICATION CENTER

AOA Wisconsin 13931 Spring Street Sturtevant, WI 53177 Phone: 1-800-262-5221 Fax: 262-886-6879

International: 262-886-1050

BRACKET & TRAY SYSTEM STANDARDS

Brackets are supplied by office, and sent to AOA Mesh Pad will have <u>Custom Composite Base</u>

TWO PIECE SYSTEM

Clear soft Vinyl w/Clear Hard Support Tray

PLACEMENT OPTIONS

☐ Standard ☐ Dr. Damon

PLEASE INDICATE WHERE TO SECTION

- ☐ Do Not Section Tray
- ☐ Section At The Midline
- ☐ Section Distal to Cuspids

PLEASE WRITE SPECIAL INSTRUCTIONS

PLEASE SHIP EXTRA	:
-------------------	---


- SHIPPING BOXES
- PRE-PAID BAGS
- PRESCRIPTION SHEETS


		_
Labial I	ndirect Bond	ina Rx


Dr	Acct #		
Address			
City, State, Zip			
Patient			
Tel #	Fax #		
E-Mail			
Shipped ————Placement Date —			
(PLACEMENT DATE SHOULD BE 1-2 DA	AYS BEFORE ACTUAL INSERTION DATE)		

NOTES:		

Standard Slot Relationship Are Illustrated Below.
Please Indicate Any Changes On Chart
Circle Teech To Be Banded By Doctor. Place "X" On Teeth Not To Be Tx.







White and Yellow: Laboratory Copy

Pink: Doctor's Copy

001-214-Fil REV E

Indiract	Danding	with Liah	st Cura	Adhaciva

Dept. √ _____

1. Paint OrthoSolo® (Ormco) on the back of the brackets in the Indirect Bonding trays. Blow excess off after 30 seconds. Immediately place a small amount of Enlight LV® (Ormco) light cure adhesive on back of the brackets. Place under an orange cover or remove from light source. **Laboratory Use Only** 2. Clean all teeth using pumice and prophy cup and rinse. Place dry angles and Nola lip retractors. 3. Micro-etch labial surfaces of posterior teeth. 5. Etch labial surfaces of posterior teeth. ΙB 6. Rinse thoroughly. Dry teeth with tooth dryer. 7. Paint OrthoSolo® on teeth. Do Not Cure. 8. ΙB 9. Place Indirect bonding tray onto mandibular arch seating firmly. Cure each bracket at least 10 seconds at the Burst Cure setting with the Optilux 501® (Demetron ΙB Corp) while pressing moderately on each bracket. 11. Repeat for maxillary arch. To remove trays, first remove hard outer tray, then gently peel soft tray from each bracket while ΙB holding a finger on bracket. Repeat on maxillary arch. Remove excess adhesive with slow speed and check interproximal contacts with floss. ΙB ΙB ΙB ΙB ΙB ΙB ΙB ΙB **SHIP RECEIVING SHIPPING** Open ______ Dept. \(\square \)______